

R15 Connecting with BT

1. On your total station, enter the Command parameter menu: F4[CFG]\4.Com Setting
2. Select: Baudrate: 9600 and Bluetooth: ON
3. Exit the page and enter the measure page
4. On your device, enter the windows Bluetooth settings
5. Delete all the old connections
6. Search new devices, until you see your Total Station
7. Connect using 1234 as password
8. Leave the settings and open your field software
9. Delete all the old connections
10. Search the instrument and connect it

NOTE: In Carlson software R1=R15; R2=R25